NAME

IO::Uncompress::Unzip - Read zip files/buffers

SYNOPSIS

```
use IO::Uncompress::Unzip qw(unzip $UnzipError) ;
my $status = unzip $input => $output [,OPTS]
or die "unzip failed: $UnzipError\n";
my $z = new IO::Uncompress::Unzip $input [OPTS]
or die "unzip failed: $UnzipError\n";
$status = $z->read($buffer)
$status = $z->read($buffer, $length)
$status = $z->read($buffer, $length, $offset)
$line = $z->getline()
$char = $z->getc()
$char = $z->ungetc()
$char = $z->opened()
$status = $z->inflateSync()
$data = $z->trailingData()
$status = $z->nextStream()
$data = $z->getHeaderInfo()
$z->tell()
$z->seek($position, $whence)
$z->binmode()
$z->fileno()
$z->eof()
$z->close()
$UnzipError ;
# IO::File mode
<$z>
read($z, $buffer);
read($z, $buffer, $length);
read($z, $buffer, $length, $offset);
tell($z)
seek($z, $position, $whence)
binmode($z)
fileno($z)
eof($z)
close($z)
```

DESCRIPTION

This module provides a Perl interface that allows the reading of zlib files/buffers.

For writing zip files/buffers, see the companion module IO::Compress::Zip.

Functional Interface

A top-level function, unzip, is provided to carry out "one-shot" uncompression between buffers and/or files. For finer control over the uncompression process, see the "OO Interface" section.

```
use IO::Uncompress::Unzip qw(unzip $UnzipError) ;
```

unzip \$input_filename_or_reference => \$output_filename_or_reference [,OPTS]
or die "unzip failed: \$UnzipError\n";

The functional interface needs Perl5.005 or better.

unzip \$input_filename_or_reference => \$output_filename_or_reference [, OPTS]
unzip expects at least two parameters, \$input_filename_or_reference and
\$output_filename_or_reference.

The input_filename_or_reference parameter

The parameter, <code>\$input_filename_or_reference</code>, is used to define the source of the compressed data.

It can take one of the following forms:

A filename

If the <\sinput_filename_or_reference> parameter is a simple scalar, it is assumed to be a filename. This file will be opened for reading and the input data will be read from it.

A filehandle

If the **\$input_filename_or_reference** parameter is a filehandle, the input data will be read from it. The string '-' can be used as an alias for standard input.

A scalar reference

If \$input_filename_or_reference is a scalar reference, the input data will be read from \$\$input_filename_or_reference.

An array reference

If \$input_filename_or_reference is an array reference, each element in the array must be a filename.

The input data will be read from each file in turn.

The complete array will be walked to ensure that it only contains valid filenames before any data is uncompressed.

An Input FileGlob string

If \$input_filename_or_reference is a string that is delimited by the characters "<" and ">" unzip will assume that it is an *input fileglob string*. The input is the list of files that match the fileglob.

See File::GlobMapper for more details.

If the \$input_filename_or_reference parameter is any other type, undef will be returned.

The output_filename_or_reference parameter

The parameter **\$output_filename_or_reference** is used to control the destination of the uncompressed data. This parameter can take one of these forms.

A filename

If the <code>\$output_filename_or_reference</code> parameter is a simple scalar, it is assumed to be a filename. This file will be opened for writing and the uncompressed data will be written to it.

A filehandle

If the **\$output_filename_or_reference** parameter is a filehandle, the uncompressed data will be written to it. The string '-' can be used as an alias for standard output.

A scalar reference

If <code>\$output_filename_or_reference</code> is a scalar reference, the uncompressed data will be stored in <code>\$\$output_filename_or_reference</code>.

An Array Reference

If <code>\$output_filename_or_reference</code> is an array reference, the uncompressed data will be pushed onto the array.

An Output FileGlob

If <code>\$output_filename_or_reference</code> is a string that is delimited by the characters "<" and ">" unzip will assume that it is an *output fileglob string*. The output is the list of files that match the fileglob.

When <code>\$output_filename_or_reference</code> is an fileglob string, <code>\$input_filename_or_reference</code> must also be a fileglob string. Anything else is an error.

See File::GlobMapper for more details.

If the \$output_filename_or_reference parameter is any other type, undef will be returned.

Notes

When <code>\$input_filename_or_reference</code> maps to multiple compressed files/buffers and <code>\$output_filename_or_reference</code> is a single file/buffer, after uncompression <code>\$output_filename_or_reference</code> will contain a concatenation of all the uncompressed data from each of the input files/buffers.

Optional Parameters

Unless specified below, the optional parameters for unzip, OPTS, are the same as those used with the OO interface defined in the "Constructor Options" section below.

AutoClose => 0|1

This option applies to any input or output data streams to unzip that are filehandles.

If AutoClose is specified, and the value is true, it will result in all input and/or output filehandles being closed once unzip has completed.

This parameter defaults to 0.

BinModeOut => 0|1

When writing to a file or filehandle, set binmode before writing to the file.

Defaults to 0.

Append \Rightarrow 0|1

The behaviour of this option is dependent on the type of output data stream.

A Buffer

If Append is enabled, all uncompressed data will be append to the end of the output buffer. Otherwise the output buffer will be cleared before any uncompressed data is written to it.

• A Filename

If Append is enabled, the file will be opened in append mode. Otherwise the contents of the file, if any, will be truncated before any uncompressed data is written to it.

A Filehandle

If Append is enabled, the filehandle will be positioned to the end of the file via a call to seek before any uncompressed data is written to it. Otherwise the file pointer will not be moved.

When Append is specified, and set to true, it will append all uncompressed data to the output data stream.

So when the output is a filehandle it will carry out a seek to the eof before writing any uncompressed data. If the output is a filename, it will be opened for appending. If the output is a buffer, all uncompressed data will be appended to the existing buffer.

Conversely when Append is not specified, or it is present and is set to false, it will operate as follows.

When the output is a filename, it will truncate the contents of the file before writing any uncompressed data. If the output is a filehandle its position will not be changed. If the output is a buffer, it will be wiped before any uncompressed data is output.

Defaults to 0.

MultiStream => 0|1

If the input file/buffer contains multiple compressed data streams, this option will uncompress the whole lot as a single data stream.

Defaults to 0.

TrailingData => \$scalar

Returns the data, if any, that is present immediately after the compressed data stream once uncompression is complete.

This option can be used when there is useful information immediately following the compressed data stream, and you don't know the length of the compressed data stream.

If the input is a buffer, trailingData will return everything from the end of the compressed data stream to the end of the buffer.

If the input is a filehandle, trailingData will return the data that is left in the filehandle input buffer once the end of the compressed data stream has been reached. You can then use the filehandle to read the rest of the input file.

Don't bother using trailingData if the input is a filename.

If you know the length of the compressed data stream before you start uncompressing, you can avoid having to use trailingData by setting the InputLength option.

Examples

Say you have a zip file, file1.zip, that only contains a single member, you can read it and write the uncompressed data to the file file1.txt like this.

```
use strict ;
use warnings ;
use IO::Uncompress::Unzip qw(unzip $UnzipError) ;

my $input = "file1.zip";
my $output = "file1.txt";
unzip $input => $output
or die "unzip failed: $UnzipError\n";
```

If you have a zip file that contains multiple members and want to read a specific member from the file, say "data1", use the Name option

```
use strict ;
use warnings ;
use IO::Uncompress::Unzip qw(unzip $UnzipError) ;

my $input = "file1.zip";
my $output = "file1.txt";
unzip $input => $output, Name => "data1"
or die "unzip failed: $UnzipError\n";
```

Alternatively, if you want to read the "data1" member into memory, use a scalar reference for the output parameter.

```
use strict ;
use warnings ;
use IO::Uncompress::Unzip qw(unzip $UnzipError) ;

my $input = "file1.zip";
my $output ;
unzip $input => \$output, Name => "data1"
or die "unzip failed: $UnzipError\n";
# $output now contains the uncompressed data
```

To read from an existing Perl filehandle, \$input, and write the uncompressed data to a buffer, \$buffer.

```
use strict ;
use warnings ;
use IO::Uncompress::Unzip qw(unzip $UnzipError) ;
use IO::File ;

my $input = new IO::File "<file1.zip"
or die "Cannot open 'file1.zip': $!\n" ;
my $buffer ;
unzip $input => \$buffer
or die "unzip failed: $UnzipError\n";
```

OO Interface

Constructor

The format of the constructor for IO::Uncompress::Unzip is shown below

```
my $z = new IO::Uncompress::Unzip $input [OPTS]
or die "IO::Uncompress::Unzip failed: $UnzipError\n";
```

Returns an IO::Uncompress::Unzip object on success and undef on failure. The variable \$UnzipError will contain an error message on failure.

If you are running Perl 5.005 or better the object, \$z, returned from IO::Uncompress::Unzip can be used exactly like an IO::File filehandle. This means that all normal input file operations can be carried out with \$z. For example, to read a line from a compressed file/buffer you can use either of these forms

```
$line = $z->getline();
$line = <$z>;
```

The mandatory parameter \$input is used to determine the source of the compressed data. This parameter can take one of three forms.

A filename

If the \$input parameter is a scalar, it is assumed to be a filename. This file will be opened for reading and the compressed data will be read from it.

A filehandle

If the **\$input** parameter is a filehandle, the compressed data will be read from it. The string '-' can be used as an alias for standard input.

A scalar reference

If \$input is a scalar reference, the compressed data will be read from \$\$input.

Constructor Options

The option names defined below are case insensitive and can be optionally prefixed by a '-'. So all of the following are valid

-AutoClose -autoclose AUTOCLOSE autoclose

OPTS is a combination of the following options:

Name => ''membername''

Open "membername" from the zip file for reading.

AutoClose => 0|1

This option is only valid when the **\$input** parameter is a filehandle. If specified, and the value is true, it will result in the file being closed once either the **close** method is called or the IO::Uncompress::Unzip object is destroyed.

This parameter defaults to 0.

MultiStream => 0|1

Treats the complete zip file/buffer as a single compressed data stream. When reading in multi-stream mode each member of the zip file/buffer will be uncompressed in turn until the end of the file/buffer is encountered.

This parameter defaults to 0.

Prime => \$string

This option will uncompress the contents of \$string before processing the input file/buffer.

This option can be useful when the compressed data is embedded in another file/data structure and it is not possible to work out where the compressed data begins without having to read the first few bytes. If this is the case, the uncompression can be *primed* with these bytes using this option.

Transparent => 0|1

If this option is set and the input file/buffer is not compressed data, the module will allow reading of it anyway.

In addition, if the input file/buffer does contain compressed data and there is non-compressed data immediately following it, setting this option will make this module treat the whole file/buffer as a single data stream.

This option defaults to 1.

BlockSize => \$num

When reading the compressed input data, IO::Uncompress::Unzip will read it in blocks of \$num bytes.

This option defaults to 4096.

InputLength => \$size

When present this option will limit the number of compressed bytes read from the input file/buffer to \$size. This option can be used in the situation where there is useful data directly after the compressed data stream and you know beforehand the exact length of the compressed data stream.

This option is mostly used when reading from a filehandle, in which case the file pointer will be left pointing to the first byte directly after the compressed data stream.

This option defaults to off.

Append => 0|1

This option controls what the read method does with uncompressed data.

If set to 1, all uncompressed data will be appended to the output parameter of the read method.

If set to 0, the contents of the output parameter of the read method will be overwritten by the uncompressed data.

Defaults to 0.

```
Strict => 0|1
```

This option controls whether the extra checks defined below are used when carrying out the decompression. When Strict is on, the extra tests are carried out, when Strict is off they are not.

The default for this option is off.

Examples

TODO

Methods

read

Usage is

```
$status = $z->read($buffer)
```

Reads a block of compressed data (the size of the compressed block is determined by the Buffer option in the constructor), uncompresses it and writes any uncompressed data into \$buffer. If the Append parameter is set in the constructor, the uncompressed data will be appended to the \$buffer parameter. Otherwise \$buffer will be overwritten.

Returns the number of uncompressed bytes written to \$buffer, zero if eof or a negative number on error.

read

Usage is

```
$status = $z->read($buffer, $length)
$status = $z->read($buffer, $length, $offset)

$status = read($z, $buffer, $length)
$status = read($z, $buffer, $length, $offset)
```

Attempt to read \$length bytes of uncompressed data into \$buffer.

The main difference between this form of the read method and the previous one, is that this one will attempt to return *exactly* \$length bytes. The only circumstances that this function will not is if end-of-file or an IO error is encountered.

Returns the number of uncompressed bytes written to **\$buffer**, zero if eof or a negative number on error.

getline

Usage is

```
$line = $z->getline()
$line = <$z>
```

Reads a single line.

This method fully supports the use of the variable \$/ (or \$INPUT_RECORD_SEPARATOR or \$RS when English is in use) to determine what constitutes an end of line. Paragraph mode, record mode and file slurp mode are all supported.

getc

Usage is

```
$char = $z->getc()
```

Read a single character.

```
ungetc
    Usage is
     $char = $z->ungetc($string)
inflateSync
    Usage is
     $status = $z->inflateSync()
    TODO
getHeaderInfo
    Usage is
     $hdr = $z->getHeaderInfo();
     @hdrs = $z->getHeaderInfo();
    This method returns either a hash reference (in scalar context) or a list or hash references (in
    array context) that contains information about each of the header fields in the compressed data
    stream(s).
tell
    Usage is
     $z->tell()
     tell $z
    Returns the uncompressed file offset.
eof
    Usage is
     $z->eof():
     eof($z);
    Returns true if the end of the compressed input stream has been reached.
seek
     $z->seek($position, $whence);
```

seek(\$z, \$position, \$whence);

Provides a sub-set of the seek functionality, with the restriction that it is only legal to seek forward in the input file/buffer. It is a fatal error to attempt to seek backward.

Note that the implementation of seek in this module does not provide true random access to a compressed file/buffer. It works by uncompressing data from the current offset in the file/buffer until it reaches the uncompressed offset specified in the parameters to seek. For very small files this may be acceptable behaviour. For large files it may cause an unacceptable delay.

The \$\text{\$\text{whence}}\$ parameter takes one the usual values, namely SEEK SET, SEEK CUR or SEEK END.

Returns 1 on success, 0 on failure.

binmode

```
Usage is

$z->binmode
binmode $z ;

This is a noop provided for completeness.

opened

$z->opened()
```

Returns true if the object currently refers to a opened file/buffer.

autoflush

```
my $prev = $z->autoflush()
my $prev = $z->autoflush(EXPR)
```

If the \$z object is associated with a file or a filehandle, this method returns the current autoflush setting for the underlying filehandle. If EXPR is present, and is non-zero, it will enable flushing after every write/print operation.

If \$z is associated with a buffer, this method has no effect and always returns undef.

Note that the special variable \$| cannot be used to set or retrieve the autoflush setting.

input line number

```
$z->input_line_number()
$z->input_line_number(EXPR)
```

Returns the current uncompressed line number. If EXPR is present it has the effect of setting the line number. Note that setting the line number does not change the current position within the file/buffer being read.

The contents of \$/ are used to determine what constitutes a line terminator.

fileno

```
$z->fileno()
fileno($z)
```

If the \$z object is associated with a file or a filehandle, fileno will return the underlying file descriptor. Once the close method is called fileno will return undef.

If the \$z object is associated with a buffer, this method will return undef.

close

```
$z->close() ;
close $z ;
```

Closes the output file/buffer.

For most versions of Perl this method will be automatically invoked if the IO::Uncompress::Unzip object is destroyed (either explicitly or by the variable with the reference to the object going out of scope). The exceptions are Perl versions 5.005 through 5.00504 and 5.8.0. In these cases, the close method will be called automatically, but not until global destruction of all live objects when the program is terminating.

Therefore, if you want your scripts to be able to run on all versions of Perl, you should call close explicitly and not rely on automatic closing.

Returns true on success, otherwise 0.

If the AutoClose option has been enabled when the IO::Uncompress::Unzip object was created, and the object is associated with a file, the underlying file will also be closed.

nextStream

Usage is

```
my $status = $z->nextStream();
```

Skips to the next compressed data stream in the input file/buffer. If a new compressed data stream is found, the eof marker will be cleared and \$. will be reset to 0.

Returns 1 if a new stream was found, 0 if none was found, and -1 if an error was encountered.

trailingData

Usage is

```
my $data = $z->trailingData();
```

Returns the data, if any, that is present immediately after the compressed data stream once uncompression is complete. It only makes sense to call this method once the end of the

compressed data stream has been encountered.

This option can be used when there is useful information immediately following the compressed data stream, and you don't know the length of the compressed data stream.

If the input is a buffer, trailingData will return everything from the end of the compressed data stream to the end of the buffer.

If the input is a filehandle, trailingData will return the data that is left in the filehandle input buffer once the end of the compressed data stream has been reached. You can then use the filehandle to read the rest of the input file.

Don't bother using trailingData if the input is a filename.

If you know the length of the compressed data stream before you start uncompressing, you can avoid having to use trailingData by setting the InputLength option in the constructor.

Importing

No symbolic constants are required by this IO::Uncompress::Unzip at present.

```
:all \; Imports {\tt unzip} and {\tt SUnzipError}. Same as doing this
```

```
use IO::Uncompress::Unzip qw(unzip $UnzipError) ;
```

EXAMPLES

Working with Net::FTP

See IO::Compress::FAQ

Walking through a zip file

The code below can be used to traverse a zip file, one compressed data stream at a time.

```
use IO::Uncompress::Unzip qw($UnzipError);

my $zipfile = "somefile.zip";
my $u = new IO::Uncompress::Unzip $zipfile
or die "Cannot open $zipfile: $UnzipError";

my $status;
for ($status = 1; $status > 0; $status = $u->nextStream())
{

my $name = $u->getHeaderInfo()->{Name};
warn "Processing member $name\n";

my $buff;
while (($status = $u->read($buff)) > 0) {
  # Do something here
}

last if $status < 0;
}

die "Error processing $zipfile: $!\n"
if $status < 0;</pre>
```

Each individual compressed data stream is read until the logical end-of-file is reached. Then nextStream is called. This will skip to the start of the next compressed data stream and clear the end-of-file flag.

It is also worth noting that nextStream can be called at any time — you don't have to wait until you have exhausted a compressed data stream before skipping to the next one.

Unzipping a complete zip file to disk

Daniel S. Sterling has written a script that uses IO::Uncompress::UnZip to read a zip file and unzip its contents to disk.

The script is available from https://gist.github.com/eqhmcow/5389877

SEE ALSO

IO::Compress::Gzip, IO::Uncompress::Gunzip, IO::Compress::Deflate, Compress::Zlib, IO::Compress::RawDeflate, IO::Uncompress::Inflate, IO::Uncompress::RawInflate, IO::Compress::Bzip2, IO::Uncompress::Bunzip2, IO::Compress::Lzma, IO::Uncompress::UnLzma, IO::Compress::Xz, IO::Uncompress::UnXz, IO::Compress::Lzop, IO::Uncompress::UnLzop, IO::Compress::Lzf, IO::Uncompress::UnLzf, IO::Uncompress::AnyInflate, IO::Uncompress::AnyUncompress

IO::Compress::FAQ

File::GlobMapper, Archive::Zip, Archive::Tar, IO::Zlib

For RFC 1950, 1951 and 1952 see http://www.faqs.org/rfcs/rfc1950.html, http://www.faqs.org/rfcs/rfc1951.html and http://www.faqs.org/rfcs/rfc1952.html

The zlib compression library was written by Jean-loup Gailly gzip@prep.ai.mit.edu and Mark Adler madler@alumni.caltech.edu.

The primary site for the zlib compression library is http://www.zlib.org.

The primary site for gzip is http://www.gzip.org.

AUTHOR

This module was written by Paul Marquess, pmqs@cpan.org.

MODIFICATION HISTORY

See the Changes file.

COPYRIGHT AND LICENSE

Copyright (c) 2005-2014 Paul Marquess. All rights reserved.

This program is free software; you can redistribute it and/or modify it under the same terms as Perl itself.