

NAME

`mysqld_multi` - manage multiple MySQL servers

SYNOPSIS

```
mysqld_multi [options] {start|stop|report} [GNR[,GNR] ...]
```

DESCRIPTION

mysqld_multi is designed to manage several **mysqld** processes that listen for connections on different Unix socket files and TCP/IP ports. It can start or stop servers, or report their current status.

mysqld_multi searches for groups named [`mysqld`*N*] in `my.cnf` (or in the file named by the `--defaults-file` option). *N* can be any positive integer. This number is referred to in the following discussion as the option group number, or *GNR*. Group numbers distinguish option groups from one another and are used as arguments to **mysqld_multi** to specify which servers you want to start, stop, or obtain a status report for. Options listed in these groups are the same that you would use in the [`mysqld`] group used for starting **mysqld**. (See, for example, Section 2.10.5, “Starting and Stopping MySQL Automatically”.) However, when using multiple servers, it is necessary that each one use its own value for options such as the Unix socket file and TCP/IP port number. For more information on which options must be unique per server in a multiple-server environment, see Section 5.6, “Running Multiple MySQL Instances on One Machine”.

To invoke **mysqld_multi**, use the following syntax:

```
shell> mysqld_multi [options] {start|stop|report} [GNR[,GNR] ...]
```

`start`, `stop`, and `report` indicate which operation to perform. You can perform the designated operation for a single server or multiple servers, depending on the *GNR* list that follows the option name. If there is no list, **mysqld_multi** performs the operation for all servers in the option file.

Each *GNR* value represents an option group number or range of group numbers. The value should be the number at the end of the group name in the option file. For example, the *GNR* for a group named [`mysqld17`] is 17. To specify a range of numbers, separate the first and last numbers by a dash. The *GNR* value 10-13 represents groups [`mysqld10`] through [`mysqld13`]. Multiple groups or group ranges can be specified on the command line, separated by commas. There must be no whitespace characters (spaces or tabs) in the *GNR* list; anything after a whitespace character is ignored.

This command starts a single server using option group [`mysqld17`]:

```
shell> mysqld_multi start 17
```

This command stops several servers, using option groups [`mysqld8`] and [`mysqld10`] through [`mysqld13`]:

```
shell> mysqld_multi stop 8,10-13
```

For an example of how you might set up an option file, use this command:

```
shell> mysqld_multi --example
```

mysqld_multi searches for option files as follows:

- With `--no-defaults`, no option files are read.
- With `--defaults-file=`*file_name*, only the named file is read.
- Otherwise, option files in the standard list of locations are read, including any file named by the `--defaults-extra-file=`*file_name* option, if one is given. (If the option is given multiple times, the last value is used.)

Option files read are searched for [`mysqld_multi`] and [`mysqld`*N*] option groups. The [`mysqld_multi`] group can be used for options to **mysqld_multi** itself. [`mysqld`*N*] groups can be used for options passed to specific **mysqld** instances.

The [`mysqld`] or [`mysqld_safe`] groups can be used for common options read by all instances of

mysqld or **mysqld_safe**. You can specify a **--defaults-file=***file_name* option to use a different configuration file for that instance, in which case the [mysqld] or [mysqld_safe] groups from that file will be used for that instance.

mysqld_multi supports the following options.

- **--help**

Display a help message and exit.

- **--config-file=***file_name*

This option is deprecated. If given, it is treated the same way as **--defaults-extra-file**, described earlier. **--config-file** was removed in MySQL 5.5.3.

- **--example**

Display a sample option file.

- **--log=***file_name*

Specify the name of the log file. If the file exists, log output is appended to it.

- **--mysqladmin=***prog_name*

The **mysqladmin** binary to be used to stop servers.

- **--mysqld=***prog_name*

The **mysqld** binary to be used. Note that you can specify **mysqld_safe** as the value for this option also. If you use **mysqld_safe** to start the server, you can include the **mysqld** or **ledir** options in the corresponding [mysqld*N*] option group. These options indicate the name of the server that **mysqld_safe** should start and the path name of the directory where the server is located. (See the descriptions for these options in [mysqld_safe\(1\)](#).)

Example:

```
[mysqld38]
mysqld = mysqld-debug
ledir = /opt/local/mysql/libexec
```

- **--no-log**

Print log information to stdout rather than to the log file. By default, output goes to the log file.

- **--password=***password*

The password of the MySQL account to use when invoking **mysqladmin**. The password value is not optional for this option, unlike for other MySQL programs.

- **--silent**

Silent mode; disable warnings.

- **--tcp-ip**

Connect to each MySQL server through the TCP/IP port instead of the Unix socket file. (If a socket file is missing, the server might still be running, but accessible only through the TCP/IP port.) By default, connections are made using the Unix socket file. This option affects stop and report operations.

- **--user=***user_name*

The user name of the MySQL account to use when invoking **mysqladmin**.

- **--verbose**

Be more verbose.

- **--version**

Display version information and exit.

Some notes about **mysqld_multi**:

- **Most important:** Before using **mysqld_multi** be sure that you understand the meanings of the options that are passed to the **mysqld** servers and *why* you would want to have separate **mysqld** processes. Beware of the dangers of using multiple **mysqld** servers with

the same data directory. Use separate data directories, unless you *know* what you are doing. Starting multiple servers with the same data directory does *not* give you extra performance in a threaded system. See Section 5.6, “Running Multiple MySQL Instances on One Machine”.

Important

Make sure that the data directory for each server is fully accessible to the Unix account that the specific **mysqld** process is started as. *Do not* use the Unix *root* account for this, unless you *know* what you are doing. See Section 6.1.5, “How to Run MySQL as a Normal User”.

- Make sure that the MySQL account used for stopping the **mysqld** servers (with the **mysqladmin** program) has the same user name and password for each server. Also, make sure that the account has the SHUTDOWN privilege. If the servers that you want to manage have different user names or passwords for the administrative accounts, you might want to create an account on each server that has the same user name and password. For example, you might set up a common `multi_admin` account by executing the following commands for each server:

```
shell> mysql -u root -S /tmp/mysql.sock -p
Enter password:
mysql> CREATE USER multi_admin@localhost IDENTIFIED BY multipass;
mysql> GRANT SHUTDOWN ON *.* TO multi_admin@localhost;
```

See Section 6.2, “The MySQL Access Privilege System”. You have to do this for each **mysqld** server. Change the connection parameters appropriately when connecting to each one. Note that the host name part of the account name must permit you to connect as `multi_admin` from the host where you want to run **mysqld_multi**.

- The Unix socket file and the TCP/IP port number must be different for every **mysqld**. (Alternatively, if the host has multiple network addresses, you can use `--bind-address` to cause different servers to listen to different interfaces.)
- The `--pid-file` option is very important if you are using **mysqld_safe** to start **mysqld** (for example, `--mysqld=mysqld_safe`). Every **mysqld** should have its own process ID file. The advantage of using **mysqld_safe** instead of **mysqld** is that **mysqld_safe** monitors its **mysqld** process and restarts it if the process terminates due to a signal sent using `kill -9` or for other reasons, such as a segmentation fault.
- You might want to use the `--user` option for **mysqld**, but to do this you need to run the **mysqld_multi** script as the Unix superuser (`root`). Having the option in the option file doesn't matter; you just get a warning if you are not the superuser and the **mysqld** processes are started under your own Unix account.

The following example shows how you might set up an option file for use with **mysqld_multi**. The order in which the **mysqld** programs are started or stopped depends on the order in which they appear in the option file. Group numbers need not form an unbroken sequence. The first and fifth `[mysqldN]` groups were intentionally omitted from the example to illustrate that you can have “gaps” in the option file. This gives you more flexibility.

```
# This is an example of a my.cnf file for mysqld_multi.
# Usually this file is located in home dir ~/.my.cnf or /etc/my.cnf
[mysqld_multi]
mysqld = /usr/local/mysql/bin/mysqld_safe
mysqladmin = /usr/local/mysql/bin/mysqladmin
user = multi_admin
password = my_password
[mysqld2]
socket = /tmp/mysql.sock2
port = 3307
pid-file = /usr/local/mysql/data2/hostname.pid2
datadir = /usr/local/mysql/data2
```

```
language = /usr/local/mysql/share/mysql/english
user = unix_user1
[mysqld3]
mysqld = /path/to/mysqld_safe
ledir = /path/to/mysqld-binary/
mysqladmin = /path/to/mysqladmin
socket = /tmp/mysql.sock3
port = 3308
pid-file = /usr/local/mysql/data3/hostname.pid3
datadir = /usr/local/mysql/data3
language = /usr/local/mysql/share/mysql/swedish
user = unix_user2
[mysqld4]
socket = /tmp/mysql.sock4
port = 3309
pid-file = /usr/local/mysql/data4/hostname.pid4
datadir = /usr/local/mysql/data4
language = /usr/local/mysql/share/mysql/estonia
user = unix_user3
[mysqld6]
socket = /tmp/mysql.sock6
port = 3311
pid-file = /usr/local/mysql/data6/hostname.pid6
datadir = /usr/local/mysql/data6
language = /usr/local/mysql/share/mysql/japanese
user = unix_user4
```

See Section 4.2.6, “Using Option Files”.

COPYRIGHT

Copyright 1997, 2018, Oracle and/or its affiliates. All rights reserved.

This documentation is free software; you can redistribute it and/or modify it only under the terms of the GNU General Public License as published by the Free Software Foundation; version 2 of the License.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with the program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA or see <http://www.gnu.org/licenses/>.

SEE ALSO

For more information, please refer to the MySQL Reference Manual, which may already be installed locally and which is also available online at <http://dev.mysql.com/doc/>.

AUTHOR

Oracle Corporation (<http://dev.mysql.com/>).