

**NAME**

**eckparam** - EC parameter manipulation and generation

**SYNOPSIS**

```
openssl eckparam [-inform DER|PEM] [-outform DER|PEM] [-in filename] [-out
filename] [-noout] [-text] [-C] [-check] [-name arg] [-list_curves] [-conv_form arg]
[-param_enc arg] [-no_seed] [-rand file(s)] [-genkey] [-engine id]
```

**DESCRIPTION**

This command is used to manipulate or generate EC parameter files.

**OPTIONS****-inform DER|PEM**

This specifies the input format. The **DER** option uses an ASN.1 DER encoded form compatible with RFC 3279 EcpkParameters. The PEM form is the default format: it consists of the **DER** format base64 encoded with additional header and footer lines.

**-outform DER|PEM**

This specifies the output format, the options have the same meaning as the **-inform** option.

**-in filename**

This specifies the input filename to read parameters from or standard input if this option is not specified.

**-out filename**

This specifies the output filename parameters to. Standard output is used if this option is not present. The output filename should **not** be the same as the input filename.

**-noout**

This option inhibits the output of the encoded version of the parameters.

**-text**

This option prints out the EC parameters in human readable form.

**-C** This option converts the EC parameters into C code. The parameters can then be loaded by calling the **get\_ec\_group\_XXX()** function.

**-check**

Validate the elliptic curve parameters.

**-name arg**

Use the EC parameters with the specified 'short' name. Use **-list\_curves** to get a list of all currently implemented EC parameters.

**-list\_curves**

If this options is specified **eckparam** will print out a list of all currently implemented EC parameters names and exit.

**-conv\_form**

This specifies how the points on the elliptic curve are converted into octet strings. Possible values are: **compressed** (the default value), **uncompressed** and **hybrid**. For more information regarding the point conversion forms please read the X9.62 standard. **Note** Due to patent issues the **compressed** option is disabled by default for binary curves and can be enabled by defining the preprocessor macro **OPENSSL\_EC\_BIN\_PT\_COMP** at compile time.

**-param\_enc arg**

This specifies how the elliptic curve parameters are encoded. Possible value are: **named\_curve**, i.e. the ec parameters are specified by a OID, or **explicit** where the ec parameters are explicitly given (see RFC 3279 for the definition of the EC parameters structures). The default value is **named\_curve**. **Note** the **implicitlyCA** alternative ,as specified in RFC 3279, is currently not implemented in OpenSSL.

**-no\_seed**

This option inhibits that the 'seed' for the parameter generation is included in the ECPParameters structure (see RFC 3279).

**-genkey**

This option will generate a EC private key using the specified parameters.

**-rand file(s)**

a file or files containing random data used to seed the random number generator, or an EGD socket (see [RAND\\_egd\(3\)](#)). Multiple files can be specified separated by a OS-dependent character. The separator is; for MS-Windows, , for OpenVMS, and : for all others.

**-engine id**

specifying an engine (by its unique **id** string) will cause **eckparam** to attempt to obtain a functional reference to the specified engine, thus initialising it if needed. The engine will then be set as the default for all available algorithms.

**NOTES**

PEM format EC parameters use the header and footer lines:

```
-----BEGIN EC PARAMETERS-----
-----END EC PARAMETERS-----
```

OpenSSL is currently not able to generate new groups and therefore **eckparam** can only create EC parameters from known (named) curves.

**EXAMPLES**

To create EC parameters with the group 'prime192v1':

```
openssl eckparam -out ec_param.pem -name prime192v1
```

To create EC parameters with explicit parameters:

```
openssl eckparam -out ec_param.pem -name prime192v1 -param_enc explicit
```

To validate given EC parameters:

```
openssl eckparam -in ec_param.pem -check
```

To create EC parameters and a private key:

```
openssl eckparam -out ec_key.pem -name prime192v1 -genkey
```

To change the point encoding to 'compressed':

```
openssl eckparam -in ec_in.pem -out ec_out.pem -conv_form compressed
```

To print out the EC parameters to standard output:

```
openssl eckparam -in ec_param.pem -noout -text
```

**SEE ALSO**

[ec\(1\)](#), [dsaparam\(1\)](#)

**HISTORY**

The eckparam command was first introduced in OpenSSL 0.9.8.

**AUTHOR**

Nils Larsch for the OpenSSL project (<http://www.openssl.org>)