

NAME

bind - bind a name to a socket

SYNOPSIS

```
#include <sys/types.h> /* See NOTES */
#include <sys/socket.h>

int bind(int sockfd, const struct sockaddr *addr,
         socklen_t addrlen);
```

DESCRIPTION

When a socket is created with [socket\(2\)](#), it exists in a name space (address family) but has no address assigned to it. **bind()** assigns the address specified by *addr* to the socket referred to by the file descriptor *sockfd*. *addrlen* specifies the size, in bytes, of the address structure pointed to by *addr*. Traditionally, this operation is called “assigning a name to a socket”.

It is normally necessary to assign a local address using **bind()** before a **SOCK_STREAM** socket may receive connections (see [accept\(2\)](#)).

The rules used in name binding vary between address families. Consult the manual entries in Section 7 for detailed information. For **AF_INET** see [ip\(7\)](#), for **AF_INET6** see [ipv6\(7\)](#), for **AF_UNIX** see [unix\(7\)](#), for **AF_APPLETALK** see [ddp\(7\)](#), for **AF_PACKET** see [packet\(7\)](#), for **AF_X25** see [x25\(7\)](#) and for **AF_NETLINK** see [netlink\(7\)](#).

The actual structure passed for the *addr* argument will depend on the address family. The *sockaddr* structure is defined as something like:

```
struct sockaddr {
    sa_family_t sa_family;
    char sa_data[14];
}
```

The only purpose of this structure is to cast the structure pointer passed in *addr* in order to avoid compiler warnings. See [EXAMPLE](#) below.

RETURN VALUE

On success, zero is returned. On error, -1 is returned, and *errno* is set appropriately.

ERRORS**EACCES**

The address is protected, and the user is not the superuser.

EADDRINUSE

The given address is already in use.

EADDRINUSE

(Internet domain sockets) The port number was specified as zero in the socket address structure, but, upon attempting to bind to an ephemeral port, it was determined that all port numbers in the ephemeral port range are currently in use. See the discussion of [/proc/sys/net/ipv4/ip_local_port_range](#) in [ip\(7\)](#).

EBADF

sockfd is not a valid descriptor.

EINVAL

The socket is already bound to an address.

EINVAL

addrlen is wrong, or *addr* is not a valid address for this socket's domain.

ENOTSOCK

sockfd is a descriptor for a file, not a socket.

The following errors are specific to UNIX domain (**AF_UNIX**) sockets:

EACCES

Search permission is denied on a component of the path prefix. (See also [path_resolution\(7\)](#).)

EADDRNOTAVAIL

A nonexistent interface was requested or the requested address was not local.

EFAULT

addr points outside the user's accessible address space.

ELOOP

Too many symbolic links were encountered in resolving *addr*.

ENAMETOOLONG

addr is too long.

ENOENT

The file does not exist.

ENOMEM

Insufficient kernel memory was available.

ENOTDIR

A component of the path prefix is not a directory.

EROFS

The socket inode would reside on a read-only filesystem.

CONFORMING TO

SVr4, 4.4BSD, POSIX.1-2001 (**bind()** first appeared in 4.2BSD).

NOTES

POSIX.1-2001 does not require the inclusion of `<sys/types.h>`, and this header file is not required on Linux. However, some historical (BSD) implementations required this header file, and portable applications are probably wise to include it.

The third argument of **bind()** is in reality an *int* (and this is what 4.x BSD and libc4 and libc5 have). Some POSIX confusion resulted in the present *socklen_t*, also used by glibc. See also [accept\(2\)](#).

BUGS

The transparent proxy options are not described.

EXAMPLE

An example of the use of **bind()** with Internet domain sockets can be found in [getaddrinfo\(3\)](#).

The following example shows how to bind a stream socket in the UNIX (**AF_UNIX**) domain, and accept connections:

```
#include <sys/socket.h>
#include <sys/un.h>
#include <stdlib.h>
#include <stdio.h>
#include <string.h>

#define MY_SOCKET_PATH /somepath
#define LISTEN_BACKLOG 50

#define handle_error(msg)
do { perror(msg); exit(EXIT_FAILURE); } while (0)

int
main(int argc, char *argv[])
{
    int sfd, cfd;
```

```

struct sockaddr_un my_addr, peer_addr;
socklen_t peer_addr_size;

sfd = socket(AF_UNIX, SOCK_STREAM, 0);
if (sfd == -1)
    handle_error(socket);

memset(&my_addr, 0, sizeof(struct sockaddr_un));
/* Clear structure */
my_addr.sun_family = AF_UNIX;
strncpy(my_addr.sun_path, MY_SOCK_PATH,
        sizeof(my_addr.sun_path) - 1);

if (bind(sfd, (struct sockaddr *) &my_addr,
        sizeof(struct sockaddr_un)) == -1)
    handle_error(bind);

if (listen(sfd, LISTEN_BACKLOG) == -1)
    handle_error(listen);

/* Now we can accept incoming connections one
at a time using accept\(2\)
*/

peer_addr_size = sizeof(struct sockaddr_un);
cfd = accept(sfd, (struct sockaddr *) &peer_addr,
            &peer_addr_size);
if (cfd == -1)
    handle_error(accept);

/* Code to deal with incoming connection(s)... */

/* When no longer required, the socket pathname, MY_SOCK_PATH
should be deleted using unlink\(2\)
or remove\(3\)
*/
}

```

SEE ALSO

[accept\(2\)](#), [connect\(2\)](#), [getsockname\(2\)](#), [listen\(2\)](#), [socket\(2\)](#), [getaddrinfo\(3\)](#), [getifaddrs\(3\)](#), [ip\(7\)](#), [ipv6\(7\)](#), [path_resolution\(7\)](#), [socket\(7\)](#), [unix\(7\)](#)

COLOPHON

This page is part of release 3.74 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <http://www.kernel.org/doc/man-pages/>.