

**NAME**

EVP\_PKEY\_set1\_RSA, EVP\_PKEY\_set1\_DSA, EVP\_PKEY\_set1\_DH,  
 EVP\_PKEY\_set1\_EC\_KEY, EVP\_PKEY\_get1\_RSA, EVP\_PKEY\_get1\_DSA,  
 EVP\_PKEY\_get1\_DH, EVP\_PKEY\_get1\_EC\_KEY, EVP\_PKEY\_assign\_RSA,  
 EVP\_PKEY\_assign\_DSA, EVP\_PKEY\_assign\_DH, EVP\_PKEY\_assign\_EC\_KEY,  
 EVP\_PKEY\_type - EVP\_PKEY assignment functions.

**SYNOPSIS**

```
#include <openssl/evp.h>

int EVP_PKEY_set1_RSA(EVP_PKEY *pkey, RSA *key);
int EVP_PKEY_set1_DSA(EVP_PKEY *pkey, DSA *key);
int EVP_PKEY_set1_DH(EVP_PKEY *pkey, DH *key);
int EVP_PKEY_set1_EC_KEY(EVP_PKEY *pkey, EC_KEY *key);

RSA *EVP_PKEY_get1_RSA(EVP_PKEY *pkey);
DSA *EVP_PKEY_get1_DSA(EVP_PKEY *pkey);
DH *EVP_PKEY_get1_DH(EVP_PKEY *pkey);
EC_KEY *EVP_PKEY_get1_EC_KEY(EVP_PKEY *pkey);

int EVP_PKEY_assign_RSA(EVP_PKEY *pkey, RSA *key);
int EVP_PKEY_assign_DSA(EVP_PKEY *pkey, DSA *key);
int EVP_PKEY_assign_DH(EVP_PKEY *pkey, DH *key);
int EVP_PKEY_assign_EC_KEY(EVP_PKEY *pkey, EC_KEY *key);

int EVP_PKEY_type(int type);
```

**DESCRIPTION**

*EVP\_PKEY\_set1\_RSA()*, *EVP\_PKEY\_set1\_DSA()*, *EVP\_PKEY\_set1\_DH()* and *EVP\_PKEY\_set1\_EC\_KEY()* set the key referenced by **pkey** to **key**.

*EVP\_PKEY\_get1\_RSA()*, *EVP\_PKEY\_get1\_DSA()*, *EVP\_PKEY\_get1\_DH()* and *EVP\_PKEY\_get1\_EC\_KEY()* return the referenced key in **pkey** or **NULL** if the key is not of the correct type.

*EVP\_PKEY\_assign\_RSA()*, *EVP\_PKEY\_assign\_DSA()*, *EVP\_PKEY\_assign\_DH()* and *EVP\_PKEY\_assign\_EC\_KEY()* also set the referenced key to **key** however these use the supplied **key** internally and so **key** will be freed when the parent **pkey** is freed.

*EVP\_PKEY\_type()* returns the type of key corresponding to the value **type**. The type of a key can be obtained with *EVP\_PKEY\_type(pkey->type)*. The return value will be *EVP\_PKEY\_RSA*, *EVP\_PKEY\_DSA*, *EVP\_PKEY\_DH* or *EVP\_PKEY\_EC* for the corresponding key types or *NID\_undef* if the key type is unassigned.

**NOTES**

In accordance with the OpenSSL naming convention the key obtained from or assigned to the **pkey** using the **1** functions must be freed as well as **pkey**.

*EVP\_PKEY\_assign\_RSA()*, *EVP\_PKEY\_assign\_DSA()*, *EVP\_PKEY\_assign\_DH()* and *EVP\_PKEY\_assign\_EC\_KEY()* are implemented as macros.

**RETURN VALUES**

*EVP\_PKEY\_set1\_RSA()*, *EVP\_PKEY\_set1\_DSA()*, *EVP\_PKEY\_set1\_DH()* and *EVP\_PKEY\_set1\_EC\_KEY()* return 1 for success or 0 for failure.

*EVP\_PKEY\_get1\_RSA()*, *EVP\_PKEY\_get1\_DSA()*, *EVP\_PKEY\_get1\_DH()* and *EVP\_PKEY\_get1\_EC\_KEY()* return the referenced key or **NULL** if an error occurred.

*EVP\_PKEY\_assign\_RSA()*, *EVP\_PKEY\_assign\_DSA()*, *EVP\_PKEY\_assign\_DH()* and *EVP\_PKEY\_assign\_EC\_KEY()* return 1 for success and 0 for failure.

EVP\_PKEY\_set1\_RSA(3SSL)

OpenSSL

EVP\_PKEY\_set1\_RSA(3SSL)

**SEE ALSO**

[EVP\\_PKEY\\_new\(3\)](#)

**HISTORY**

TBA