

**NAME**

getpwent, setpwent, endpwent - get password file entry

**SYNOPSIS**

```
#include <sys/types.h>
#include <pwd.h>

struct passwd *getpwent(void);

void setpwent(void);

void endpwent(void);
```

Feature Test Macro Requirements for glibc (see [feature\\_test\\_macros\(7\)](#)):

```
getpwent(), setpwent(), endpwent():
    _BSD_SOURCE || _SVID_SOURCE || _XOPEN_SOURCE >= 500 ||
    _XOPEN_SOURCE && _XOPEN_SOURCE_EXTENDED
```

**DESCRIPTION**

The **getpwent()** function returns a pointer to a structure containing the broken-out fields of a record from the password database (e.g., the local password file */etc/passwd*, NIS, and LDAP). The first time **getpwent()** is called, it returns the first entry; thereafter, it returns successive entries.

The **setpwent()** function rewinds to the beginning of the password database.

The **endpwent()** function is used to close the password database after all processing has been performed.

The *passwd* structure is defined in *<pwd.h>* as follows:

```
struct passwd {
    char *pw_name; /* username */
    char *pw_passwd; /* user password */
    uid_t pw_uid; /* user ID */
    gid_t pw_gid; /* group ID */
    char *pw_gecos; /* user information */
    char *pw_dir; /* home directory */
    char *pw_shell; /* shell program */
};
```

When [shadow\(5\)](#) passwords are enabled (which is default on many GNU/Linux installations) the content of *pw\_passwd* is usually not very useful. In such a case most passwords are stored in a separate file.

The variable *pw\_shell* may be empty, in which case the system will execute the default shell (*/bin/sh*) for the user.

For more information about the fields of this structure, see [passwd\(5\)](#).

**RETURN VALUE**

The **getpwent()** function returns a pointer to a *passwd* structure, or NULL if there are no more entries or an error occurred. If an error occurs, *errno* is set appropriately. If one wants to check *errno* after the call, it should be set to zero before the call.

The return value may point to a static area, and may be overwritten by subsequent calls to **getpwent()**, [getpwnam\(3\)](#), or [getpwuid\(3\)](#). (Do not pass the returned pointer to [free\(3\)](#).)

**ERRORS****EINTR**

A signal was caught.

**EIO** I/O error.

**EMFILE**

The maximum number (**OPEN\_MAX**) of files was open already in the calling process.

**ENFILE**

The maximum number of files was open already in the system.

**ENOMEM**

Insufficient memory to allocate *passwd* structure.

**ERANGE**

Insufficient buffer space supplied.

**FILES**

*/etc/passwd*

local password database file

**ATTRIBUTES****Multithreading (see pthreads(7))**

The **getpwent()** function is not thread-safe.

The **setpwent()** and **endpwent()** functions are thread-safe.

**CONFORMING TO**

SVr4, 4.3BSD, POSIX.1-2001. The *pw\_gecos* field is not specified in POSIX, but is present on most implementations.

**SEE ALSO**

[fgetpwent\(3\)](#), [getpw\(3\)](#), [getpwent\\_r\(3\)](#), [getpwnam\(3\)](#), [getpwuid\(3\)](#), [putpwent\(3\)](#), [shadow\(5\)](#), [passwd\(5\)](#)

**COLOPHON**

This page is part of release 3.74 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <http://www.kernel.org/doc/man-pages/>.