

NAME

logb, logbf, logbl - get exponent of a floating-point value

SYNOPSIS

```
#include <math.h>

double logb(double x);
float logbf(float x);
long double logbl(long double x);
```

Link with *-lm*.

Feature Test Macro Requirements for glibc (see [feature_test_macros\(7\)](#)):

```
logb():
    _BSD_SOURCE || _SVID_SOURCE || _XOPEN_SOURCE >= 500 ||
    _XOPEN_SOURCE && _XOPEN_SOURCE_EXTENDED || _ISOC99_SOURCE ||
    _POSIX_C_SOURCE >= 200112L;
    or cc -std=c99

logbf(), logbl():
    _BSD_SOURCE || _SVID_SOURCE || _XOPEN_SOURCE >= 600 || _ISOC99_SOURCE ||
    _POSIX_C_SOURCE >= 200112L;
    or cc -std=c99
```

DESCRIPTION

These functions extract the exponent from the internal floating-point representation of *x* and return it as a floating-point value. The integer constant **FLT_RADIX**, defined in *<float.h>*, indicates the radix used for the system's floating-point representation. If **FLT_RADIX** is 2, **logb(x)** is equal to **floor(log2(x))**, except that it is probably faster.

If *x* is subnormal, **logb()** returns the exponent *x* would have if it were normalized.

RETURN VALUE

On success, these functions return the exponent of *x*.

If *x* is a NaN, a NaN is returned.

If *x* is zero, then a pole error occurs, and the functions return **-HUGE_VAL**, **-HUGE_VALF**, or **-HUGE_VALL**, respectively.

If *x* is negative infinity or positive infinity, then positive infinity is returned.

ERRORS

See [math_error\(7\)](#) for information on how to determine whether an error has occurred when calling these functions.

The following errors can occur:

Pole error: *x* is 0

A divide-by-zero floating-point exception (**FE_DIVBYZERO**) is raised.

These functions do not set *errno*.

ATTRIBUTES

Multithreading (see [pthreads\(7\)](#))

The **logb()**, **logbf()**, and **logbl()** functions are thread-safe.

CONFORMING TO

C99, POSIX.1-2001.

SEE ALSO

[ilogb\(3\)](#), [log\(3\)](#)

COLOPHON

This page is part of release 3.74 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <http://www.kernel.org/doc/man-pages/>.