

NAME

BN_BLINDING_new, BN_BLINDING_free, BN_BLINDING_update, BN_BLINDING_convert, BN_BLINDING_invert, BN_BLINDING_convert_ex, BN_BLINDING_invert_ex, BN_BLINDING_get_thread_id, BN_BLINDING_set_thread_id, BN_BLINDING_thread_id, BN_BLINDING_get_flags, BN_BLINDING_set_flags, BN_BLINDING_create_param - blinding related BIGNUM functions.

SYNOPSIS

```
#include <openssl/bn.h>
```

```
BN_BLINDING *BN_BLINDING_new(const BIGNUM *A, const BIGNUM *Ai,
    BIGNUM *mod);
void BN_BLINDING_free(BN_BLINDING *b);
int BN_BLINDING_update(BN_BLINDING *b, BN_CTX *ctx);
int BN_BLINDING_convert(BIGNUM *n, BN_BLINDING *b, BN_CTX *ctx);
int BN_BLINDING_invert(BIGNUM *n, BN_BLINDING *b, BN_CTX *ctx);
int BN_BLINDING_convert_ex(BIGNUM *n, BIGNUM *r, BN_BLINDING *b,
    BN_CTX *ctx);
int BN_BLINDING_invert_ex(BIGNUM *n, const BIGNUM *r, BN_BLINDING *b,
    BN_CTX *ctx);
#ifdef OPENSSL_NO_DEPRECATED
unsigned long BN_BLINDING_get_thread_id(const BN_BLINDING *);
void BN_BLINDING_set_thread_id(BN_BLINDING *, unsigned long);
#endif
CRYPTO_THREADID *BN_BLINDING_thread_id(BN_BLINDING *);
unsigned long BN_BLINDING_get_flags(const BN_BLINDING *);
void BN_BLINDING_set_flags(BN_BLINDING *, unsigned long);
BN_BLINDING *BN_BLINDING_create_param(BN_BLINDING *b,
    const BIGNUM *e, BIGNUM *m, BN_CTX *ctx,
    int (*bn_mod_exp)(BIGNUM *r, const BIGNUM *a, const BIGNUM *p,
    const BIGNUM *m, BN_CTX *ctx, BN_MONT_CTX *m_ctx),
    BN_MONT_CTX *m_ctx);
```

DESCRIPTION

BN_BLINDING_new() allocates a new **BN_BLINDING** structure and copies the **A** and **Ai** values into the newly created **BN_BLINDING** object.

BN_BLINDING_free() frees the **BN_BLINDING** structure.

BN_BLINDING_update() updates the **BN_BLINDING** parameters by squaring the **A** and **Ai** or, after specific number of uses and if the necessary parameters are set, by re-creating the blinding parameters.

BN_BLINDING_convert_ex() multiplies **n** with the blinding factor **A**. If **r** is not NULL a copy of the inverse blinding factor **Ai** will be returned in **r** (this is useful if a **RSA** object is shared among several threads). *BN_BLINDING_invert_ex()* multiplies **n** with the inverse blinding factor **Ai**. If **r** is not NULL it will be used as the inverse blinding.

BN_BLINDING_convert() and *BN_BLINDING_invert()* are wrapper functions for *BN_BLINDING_convert_ex()* and *BN_BLINDING_invert_ex()* with **r** set to NULL.

BN_BLINDING_thread_id() provides access to the **CRYPTO_THREADID** object within the **BN_BLINDING** structure. This is to help users provide proper locking if needed for multi-threaded use. The “thread id” object of a newly allocated **BN_BLINDING** structure is initialised to the thread id in which *BN_BLINDING_new()* was called.

BN_BLINDING_get_flags() returns the **BN_BLINDING** flags. Currently there are two supported flags: **BN_BLINDING_NO_UPDATE** and **BN_BLINDING_NO_RECREATE**. **BN_BLINDING_NO_UPDATE** inhibits the automatic update of the **BN_BLINDING**

parameters after each use and **BN_BLINDING_NO_RECREATE** inhibits the automatic re-creation of the **BN_BLINDING** parameters after a fixed number of uses (currently 32). In newly allocated **BN_BLINDING** objects no flags are set. *BN_BLINDING_set_flags()* sets the **BN_BLINDING** parameters flags.

BN_BLINDING_create_param() creates new **BN_BLINDING** parameters using the exponent **e** and the modulus **m**. **bn_mod_exp** and **m_ctx** can be used to pass special functions for exponentiation (normally *BN_mod_exp_mont()* and **BN_MONT_CTX**).

RETURN VALUES

BN_BLINDING_new() returns the newly allocated **BN_BLINDING** structure or NULL in case of an error.

BN_BLINDING_update(), *BN_BLINDING_convert()*, *BN_BLINDING_invert()*, *BN_BLINDING_convert_ex()* and *BN_BLINDING_invert_ex()* return 1 on success and 0 if an error occurred.

BN_BLINDING_thread_id() returns a pointer to the thread id object within a **BN_BLINDING** object.

BN_BLINDING_get_flags() returns the currently set **BN_BLINDING** flags (a **unsigned long** value).

BN_BLINDING_create_param() returns the newly created **BN_BLINDING** parameters or NULL on error.

SEE ALSO

[bn\(3\)](#)

HISTORY

BN_BLINDING_thread_id was first introduced in OpenSSL 1.0.0, and it deprecates **BN_BLINDING_set_thread_id** and **BN_BLINDING_get_thread_id**.

BN_BLINDING_convert_ex, **BN_BLINDING_invert_ex**, **BN_BLINDING_get_thread_id**, **BN_BLINDING_set_thread_id**, **BN_BLINDING_set_flags**, **BN_BLINDING_get_flags** and **BN_BLINDING_create_param** were first introduced in OpenSSL 0.9.8

AUTHOR

Nils Larsch for the OpenSSL project (<http://www.openssl.org>).