

NAME

`BN_mod_mul_montgomery`, `BN_MONT_CTX_new`, `BN_MONT_CTX_init`,
`BN_MONT_CTX_free`, `BN_MONT_CTX_set`, `BN_MONT_CTX_copy`, `BN_from_montgomery`,
`BN_to_montgomery` - Montgomery multiplication

SYNOPSIS

```
#include <openssl/bn.h>

BN_MONT_CTX *BN_MONT_CTX_new(void);
void BN_MONT_CTX_init(BN_MONT_CTX *ctx);
void BN_MONT_CTX_free(BN_MONT_CTX *mont);

int BN_MONT_CTX_set(BN_MONT_CTX *mont, const BIGNUM *m, BN_CTX *ctx);
BN_MONT_CTX *BN_MONT_CTX_copy(BN_MONT_CTX *to, BN_MONT_CTX *from);

int BN_mod_mul_montgomery(BIGNUM *r, BIGNUM *a, BIGNUM *b,
BN_MONT_CTX *mont, BN_CTX *ctx);

int BN_from_montgomery(BIGNUM *r, BIGNUM *a, BN_MONT_CTX *mont,
BN_CTX *ctx);

int BN_to_montgomery(BIGNUM *r, BIGNUM *a, BN_MONT_CTX *mont,
BN_CTX *ctx);
```

DESCRIPTION

These functions implement Montgomery multiplication. They are used automatically when [BN_mod_exp\(3\)](#) is called with suitable input, but they may be useful when several operations are to be performed using the same modulus.

`BN_MONT_CTX_new()` allocates and initializes a `BN_MONT_CTX` structure. `BN_MONT_CTX_init()` initializes an existing uninitialized `BN_MONT_CTX`.

`BN_MONT_CTX_set()` sets up the `mont` structure from the modulus `m` by precomputing its inverse and a value `R`.

`BN_MONT_CTX_copy()` copies the `BN_MONT_CTX` `from` to `to`.

`BN_MONT_CTX_free()` frees the components of the `BN_MONT_CTX`, and, if it was created by `BN_MONT_CTX_new()`, also the structure itself.

`BN_mod_mul_montgomery()` computes $\text{Mont}(a,b) := a \cdot b \cdot R^{-1}$ and places the result in `r`.

`BN_from_montgomery()` performs the Montgomery reduction $r = a \cdot R^{-1}$.

`BN_to_montgomery()` computes $\text{Mont}(a, R^2)$, i.e. $a \cdot R$. Note that `a` must be non-negative and smaller than the modulus.

For all functions, `ctx` is a previously allocated `BN_CTX` used for temporary variables.

The `BN_MONT_CTX` structure is defined as follows:

```
typedef struct bn_mont_ctx_st
{
    int ri; /* number of bits in R */
    BIGNUM RR; /* R2 (used to convert to Montgomery form) */
    BIGNUM N; /* The modulus */
    BIGNUM Ni; /* R*(1/R mod N) - N*Ni = 1
    * (Ni is only stored for bignum algorithm) */
    BN_ULONG n0; /* least significant word of Ni */
    int flags;
} BN_MONT_CTX;
```

BN_to_montgomery() is a macro.

RETURN VALUES

BN_MONT_CTX_new() returns the newly allocated **BN_MONT_CTX**, and NULL on error.

BN_MONT_CTX_init() and *BN_MONT_CTX_free()* have no return values.

For the other functions, 1 is returned for success, 0 on error. The error codes can be obtained by [*ERR_get_error\(3\)*](#).

WARNING

The inputs must be reduced modulo **m**, otherwise the result will be outside the expected range.

SEE ALSO

[*bn\(3\)*](#), [*ERR_get_error\(3\)*](#), [*BN_add\(3\)*](#), [*BN_CTX_new\(3\)*](#)

HISTORY

BN_MONT_CTX_new(), *BN_MONT_CTX_free()*, *BN_MONT_CTX_set()*,
BN_mod_mul_montgomery(), *BN_from_montgomery()* and *BN_to_montgomery()* are available in all versions of SSLeay and OpenSSL.

BN_MONT_CTX_init() and *BN_MONT_CTX_copy()* were added in SSLeay 0.9.1b.