

NAME

grolj4 - groff driver for HP Laserjet 4 family

SYNOPSIS

grolj4 [**-lv**] [**-d**[*n*]] [**-cn**] [**-ppaper_size**] [**-wn**] [**-F dir**] [*files...*]

DESCRIPTION

grolj4 is a driver for **groff** that produces output in PCL5 format suitable for an HP Laserjet 4 printer.

There is an additional drawing command available:

D'R dh dv'

Draw a rule (solid black rectangle), with one corner at the current position, and the diagonally opposite corner at the current position +(*dh,dv*). Afterwards the current position will be at the opposite corner. This generates a PCL fill rectangle command, and so will work on printers that do not support HPGL/2 unlike the other **D** commands.

OPTIONS

It is possible to have whitespace between a command line option and its parameter.

- cn** Print *n* copies of each page.
- l** Print the document with a landscape orientation.
- d** [*n*] Use duplex mode *n*: 1 is long-side binding; 2 is short-side binding; default is 1.
- psize** Set the paper size to *size*, which must be one of letter, legal, executive, a4, com10, monarch, c5, b5, dl.
- v** Print the version number.
- wn** Set the default line thickness to *n* thousandths of an em. If this option isnt specified, the line thickness defaults to 0.04 em.
- Fdir** Prepend directory *dir/devname* to the search path for font and device description files; *name* is the name of the device, usually **lj4**.

The following four commands are available additionally in the font description files:

pclweight *N*

The integer value *N* must be in the range -7 to +7; default is 0.

pclstyle *N*

The integer value *N* must be in the range 0 to 32767; default is 0.

pclproportional *N*

A boolean flag which can be either 0 or 1; default is 0.

pcltypeface *N*

The integer value *N* must be in the range 0 to 65535; default is 0.

ENVIRONMENT

GROFF_FONT_PATH

A list of directories in which to search for the **devname** directory in addition to the default ones. See [troff\(1\)](#) and [groff_font\(5\)](#) for more details.

FILES

/usr/share/groff/1.22.3/font/devlj4/DESC

Device description file.

/usr/share/groff/1.22.3/font/devlj4/F

Font description file for font *F*.

/usr/share/groff/1.22.3/tmac/lj4.tmac

Macros for use with **grolj4**.

BUGS

Small dots.

SEE ALSO

[lj4_font\(5\)](#), [groff\(1\)](#), [troff\(1\)](#), [groff_out\(5\)](#), [groff_font\(5\)](#), [groff_char\(7\)](#)

COPYING

Copyright 1994-2014 Free Software Foundation, Inc.

Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies.

Permission is granted to copy and distribute modified versions of this manual under the conditions for verbatim copying, provided that the entire resulting derived work is distributed under the terms of a permission notice identical to this one.

Permission is granted to copy and distribute translations of this manual into another language, under the above conditions for modified versions, except that this permission notice may be included in translations approved by the Free Software Foundation instead of in the original English.