

NAME

aclocal - manual page for aclocal 1.14.1

SYNOPSIS

aclocal [*OPTION*]...

DESCRIPTION

Generate 'aclocal.m4' by scanning 'configure.ac' or 'configure.in'

OPTIONS

--automake-acdir=DIR

directory holding automake-provided m4 files

--system-acdir=DIR

directory holding third-party system-wide files

--diff[=COMMAND]

run COMMAND [diff -u] on M4 files that would be changed (implies **--install** and **--dry-run**)

--dry-run

pretend to, but do not actually update any file

--force

always update output file

--help print this help, then exit

-I DIR add directory to search list for .m4 files

--install

copy third-party files to the first **-I** directory

--output=FILE

put output in FILE (default aclocal.m4)

--print-ac-dir

print name of directory holding system-wide third-party m4 files, then exit

--verbose

don't be silent

--version

print version number, then exit

-W, --warnings=CATEGORY

report the warnings falling in CATEGORY

Warning categories include:

syntax dubious syntactic constructs (default)

unsupported

unknown macros (default)

all all the warnings (default)

no-CATEGORY

turn off warnings in CATEGORY

none turn off all the warnings

error treat warnings as errors

AUTHOR

Written by Tom Tromej <tromej@redhat.com>

and Alexandre Duret-Lutz <adl@gnu.org>.

REPORTING BUGS

Report bugs to <bug-automake@gnu.org>.

GNU Automake home page: <<http://www.gnu.org/software/automake/>>.

General help using GNU software: <<http://www.gnu.org/gethelp/>>.

COPYRIGHT

Copyright 2013 Free Software Foundation, Inc. License GPLv2+: GNU GPL version 2 or later
<<http://gnu.org/licenses/gpl-2.0.html>>

This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

SEE ALSO

The full documentation for **aclocal** is maintained as a Texinfo manual. If the **info** and **aclocal** programs are properly installed at your site, the command

info aclocal

should give you access to the complete manual.