

NAME

aclocal - manual page for aclocal 1.14.1

SYNOPSIS

aclocal [*OPTION*]...

DESCRIPTION

Generate 'aclocal.m4' by scanning 'configure.ac' or 'configure.in'

OPTIONS

- automake-acdir=DIR**
directory holding automake-provided m4 files
- system-acdir=DIR**
directory holding third-party system-wide files
- diff[=COMMAND]**
run COMMAND [diff -u] on M4 files that would be changed (implies **--install** and **--dry-run**)
- dry-run**
pretend to, but do not actually update any file
- force**
always update output file
- help** print this help, then exit
- I DIR** add directory to search list for .m4 files
- install**
copy third-party files to the first **-I** directory
- output=FILE**
put output in FILE (default aclocal.m4)
- print-ac-dir**
print name of directory holding system-wide third-party m4 files, then exit
- verbose**
don't be silent
- version**
print version number, then exit
- W, --warnings=CATEGORY**
report the warnings falling in CATEGORY

Warning categories include:

- syntax dubious syntactic constructs (default)
- unsupported
unknown macros (default)
- all all the warnings (default)
- no-CATEGORY
turn off warnings in CATEGORY
- none turn off all the warnings
- error treat warnings as errors

AUTHOR

Written by Tom Tromeey <tromeey@redhat.com>
and Alexandre Duret-Lutz <adl@gnu.org>.

REPORTING BUGS

Report bugs to <bug-automake@gnu.org>.

GNU Automake home page: <<http://www.gnu.org/software/automake/>>.

General help using GNU software: <<http://www.gnu.org/gethelp/>>.

COPYRIGHT

Copyright 2013 Free Software Foundation, Inc. License GPLv2+: GNU GPL version 2 or later
<<http://gnu.org/licenses/gpl-2.0.html>>

This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

SEE ALSO

The full documentation for **aclocal** is maintained as a Texinfo manual. If the **info** and **aclocal** programs are properly installed at your site, the command

info aclocal

should give you access to the complete manual.