

NAME

BN_set_bit, BN_clear_bit, BN_is_bit_set, BN_mask_bits, BN_lshift, BN_lshift1, BN_rshift, BN_rshift1 - bit operations on BIGNUMs

SYNOPSIS

```
#include <openssl/bn.h>

int BN_set_bit(BIGNUM *a, int n);
int BN_clear_bit(BIGNUM *a, int n);

int BN_is_bit_set(const BIGNUM *a, int n);

int BN_mask_bits(BIGNUM *a, int n);

int BN_lshift(BIGNUM *r, const BIGNUM *a, int n);
int BN_lshift1(BIGNUM *r, BIGNUM *a);

int BN_rshift(BIGNUM *r, BIGNUM *a, int n);
int BN_rshift1(BIGNUM *r, BIGNUM *a);
```

DESCRIPTION

BN_set_bit() sets bit **n** in **a** to 1 ($a|=1<<n$). The number is expanded if necessary.

BN_clear_bit() sets bit **n** in **a** to 0 ($a&=(1<<n)$). An error occurs if **a** is shorter than **n** bits.

BN_is_bit_set() tests if bit **n** in **a** is set.

BN_mask_bits() truncates **a** to an **n** bit number ($a&=((0)>>n)$). An error occurs if **a** already is shorter than **n** bits.

BN_lshift() shifts **a** left by **n** bits and places the result in **r** ($r=a*2^n$). *BN_lshift1()* shifts **a** left by one and places the result in **r** ($r=2*a$).

BN_rshift() shifts **a** right by **n** bits and places the result in **r** ($r=a/2^n$). *BN_rshift1()* shifts **a** right by one and places the result in **r** ($r=a/2$).

For the shift functions, **r** and **a** may be the same variable.

RETURN VALUES

BN_is_bit_set() returns 1 if the bit is set, 0 otherwise.

All other functions return 1 for success, 0 on error. The error codes can be obtained by [ERR_get_error\(3\)](#).

SEE ALSO

[bn\(3\)](#), [BN_num_bytes\(3\)](#), [BN_add\(3\)](#)

HISTORY

BN_set_bit(), *BN_clear_bit()*, *BN_is_bit_set()*, *BN_mask_bits()*, *BN_lshift()*, *BN_lshift1()*, *BN_rshift()*, and *BN_rshift1()* are available in all versions of SSLeay and OpenSSL.